

BBB Server Outputs

HOST: RCPT-Host-03

```
[mdcadmin@RCPT-Host-03 ~]$ cat nmcli.log
bond0: connected to bond0
["bond0"]
["bond, 8C:84:74:FD:88:DE, sw, mtu 1500"]
["ip4 default"]
["inet4 172.18.0.23/24"]
["route4 default via 172.18.0.1 metric 300"]
["route4 172.18.0.0/24 metric 300"]
["inet6 fe80::8e84:74ff:fe8d:88de/64"]
["route6 fe80::/64 metric 1024"]

virbr0: connected (externally) to virbr0
["virbr0"]
["bridge, 52:54:00:26:94:37, sw, mtu 1500"]
["inet4 192.168.122.1/24"]
["route4 192.168.122.0/24 metric 0"]

vnet37: connected (externally) to vnet37
["vnet37"]
["tun, FE:54:00:39:19:3B, sw, mtu 9216"]
["master br2"]
["inet6 fe80::fc54:ff:fe39:193b/64"]
["route6 fe80::/64 metric 256"]

vnet38: connected (externally) to vnet38
["vnet38"]
["tun, FE:54:00:DF:48:20, sw, mtu 9216"]
["master br2"]
["inet6 fe80::fc54:ff:fedf:4820/64"]
["route6 fe80::/64 metric 256"]
```

vnet39: connected (externally) to vnet39

□"vnet39"

□tun, FE:54:00:56:9B:F5, sw, mtu 9216

□master br3

□inet6 fe80::fc54:ff:fe56:9bf5/64

□route6 fe80::/64 metric 256

vnet42: connected (externally) to vnet42

□"vnet42"

□tun, FE:54:00:5D:E2:16, sw, mtu 9216

□master br2

□inet6 fe80::fc54:ff:fe5d:e216/64

□route6 fe80::/64 metric 256

vnet43: connected (externally) to vnet43

□"vnet43"

□tun, FE:54:00:6E:3B:20, sw, mtu 9216

□master br2

□inet6 fe80::fc54:ff:fe6e:3b20/64

□route6 fe80::/64 metric 256

vnet46: connected (externally) to vnet46

□"vnet46"

□tun, FE:54:00:F5:D4:68, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:fef5:d468/64

□route6 fe80::/64 metric 256

vnet47: connected (externally) to vnet47

□"vnet47"

□tun, FE:54:00:B3:EE:80, sw, mtu 9216

□master br2

□inet6 fe80::fc54:ff:feb3:ee80/64

□route6 fe80::/64 metric 256

vnet48: connected (externally) to vnet48

□"vnet48"

□tun, FE:54:00:81:87:68, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:fe81:8768/64

□route6 fe80::/64 metric 256

vnet49: connected (externally) to vnet49

□"vnet49"

□tun, FE:54:00:69:8F:A2, sw, mtu 9216

□master br3

□inet6 fe80::fc54:ff:fe69:8fa2/64

□route6 fe80::/64 metric 256

vnet50: connected (externally) to vnet50

□"vnet50"

□tun, FE:54:00:17:BC:71, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:fe17:bc71/64

□route6 fe80::/64 metric 256

vnet51: connected (externally) to vnet51

□"vnet51"

□tun, FE:54:00:BF:6F:37, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:febf:6f37/64

□route6 fe80::/64 metric 256

vnet52: connected (externally) to vnet52

□"vnet52"

□tun, FE:54:00:BD:64:34, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:febd:6434/64

□route6 fe80::/64 metric 256

vnet53: connected (externally) to vnet53

□"vnet53"

□tun, FE:54:00:06:3A:3A, sw, mtu 9216

□master br2

□inet6 fe80::fc54:ff:fe06:3a3a/64

□route6 fe80::/64 metric 256

vnet54: connected (externally) to vnet54

□"vnet54"

□tun, FE:54:00:E6:4C:C4, sw, mtu 1500

□master br1

□inet6 fe80::fc54:ff:fee6:4cc4/64

□route6 fe80::/64 metric 256

bond1: connected to bond1

□"bond1"

□bond, 8C:84:74:FD:88:DC, sw, mtu 1500

□master br1

bond2: connected to bond2

□"bond2"

□bond, 8C:84:74:47:86:00, sw, mtu 9216

□master br2

bond3: connected to bond3

□"bond3"

□bond, 8C:84:74:47:86:02, sw, mtu 9216

□master br3

br1: connected to br1

□"br1"

□bridge, 8C:84:74:FD:88:DC, sw, mtu 1500

br2: connected to br2

□"br2"

□bridge, 8C:84:74:47:86:00, sw, mtu 9216

br3: connected to br3

□"br3"

□bridge, 8C:84:74:47:86:02, sw, mtu 9216

eno12399np0: connected to bond2-slave1

□"Broadcom and subsidiaries BCM57454 NetXtreme-E 10Gb/25Gb/40Gb/50Gb/100Gb"

□ethernet (bnxt_en), 8C:84:74:47:86:00, hw, mtu 9216

□master bond2

eno12409np1: connected to bond2-slave0

□"Broadcom and subsidiaries BCM57454 NetXtreme-E 10Gb/25Gb/40Gb/50Gb/100Gb"

□ethernet (bnxt_en), 8C:84:74:47:86:00, hw, mtu 9216

□master bond2

eno12419np2: connected to bond3-slave0

□"Broadcom and subsidiaries BCM57454 NetXtreme-E 10Gb/25Gb/40Gb/50Gb/100Gb"

□ethernet (bnxt_en), 8C:84:74:47:86:02, hw, mtu 9216

□master bond3

eno12429np3: connected to bond3-slave1

□"Broadcom and subsidiaries BCM57454 NetXtreme-E 10Gb/25Gb/40Gb/50Gb/100Gb"

□ethernet (bnxt_en), 8C:84:74:47:86:02, hw, mtu 9216

□master bond3

ens6f0: connected to bond1-slave0

□"Broadcom and subsidiaries NetXtreme BCM5719"

□ethernet (tg3), 8C:84:74:FD:88:DC, hw, mtu 1500

□master bond1

ens6f1: connected to bond1-slave1

□"Broadcom and subsidiaries NetXtreme BCM5719"

□ethernet (tg3), 8C:84:74:FD:88:DC, hw, mtu 1500

□master bond1

ens6f2: connected to bond0-slave1

□"Broadcom and subsidiaries NetXtreme BCM5719"

□ethernet (tg3), 8C:84:74:FD:88:DE, hw, mtu 1500

□master bond0

ens6f3: connected to bond0-slave0

□"Broadcom and subsidiaries NetXtreme BCM5719"

□ethernet (tg3), 8C:84:74:FD:88:DE, hw, mtu 1500

□master bond0

vsr_nrc_mgt: connected (externally) to vsr_nrc_mgt

□"vsr_nrc_mgt"

□tun, FE:54:00:70:E2:93, sw, mtu 1500

□master br1

lo: unmanaged

□"lo"

□loopback (unknown), 00:00:00:00:00:00, sw, mtu 65536

```
vsr_nrc_p1: unmanaged
[]"vsr_nrc_p1"
[]tun, FE:54:00:03:CB:0E, sw, mtu 1500
```

DNS configuration:

```
[]servers: 8.8.8.8 8.8.4.4 1.1.1.1
[]interface: bond0
```

Use "nmcli device show" to get complete information about known devices and
"nmcli connection show" to get an overview on active connection profiles.

Consult nmcli(1) and nmcli-examples(7) manual pages for complete usage details.

VM: RCPT-NFM-P-COLLO

```
[mdcadmin@rcpt-nfm-p-collo ~]$ nmcli
enpls0: connected to enpls0
    "Red Hat Virtio"
    ethernet (virtio_net), 52:54:00:DF:48:20, hw, mtu 9216
    ip4 default
    inet4 172.18.1.62/24
    route4 172.18.1.0/24 metric 100
    route4 default via 172.18.1.1 metric 100
    route4 172.18.51.0/24 via 172.18.1.4 metric 100

virbr0: connected (externally) to virbr0
    "virbr0"
    bridge, 52:54:00:AB:46:FE, sw, mtu 1500
    inet4 192.168.122.1/24
    route4 192.168.122.0/24 metric 0

enp7s0: connected to enp7s0
    "Red Hat Virtio"
    ethernet (virtio_net), 52:54:00:56:9B:F5, hw, mtu 9216
    inet4 172.18.2.59/24
    route4 172.18.2.0/24 metric 101
    route4 72.16.20.0/24 via 172.18.2.4 metric 0
```

```
route4 172.23.0.0/16 via 172.18.2.4 metric 0
route4 172.22.0.0/16 via 172.18.2.4 metric 0
```

```
enp8s0: disconnected
      "Red Hat Virtio"
      1 connection available
      ethernet (virtio_net), 52:54:00:F5:D4:68, hw, mtu 1500
```

```
lo: unmanaged
     "lo"
     loopback (unknown), 00:00:00:00:00:00, sw, mtu 65536
```

```
DNS configuration:
      servers: 8.8.8.8 8.8.4.4
      interface: enp1s0
```

VM: RCPT-NSP-07

```
[mdcadmin@rcpt-nsp-07 ~]$ nmcli
enp1s0: connected to enp1s0
      "Red Hat Virtio 1.0"
      ethernet (virtio_net), 52:54:00:E6:4C:C4, hw, mtu 1500
      ip4 default
      inet4 172.18.1.57/24
      route4 172.18.1.0/24 metric 105
      route4 default via 172.18.1.1 metric 105
      route4 172.18.51.0/24 via 172.18.1.4 metric 105

enp7s0: connected to enp7s0
      "Red Hat Virtio 1.0"
      ethernet (virtio_net), 52:54:00:06:3A:3A, hw, mtu 1500
      inet4 172.18.2.57/24
      route4 172.18.2.0/24 metric 103
      route4 172.16.20.0/24 via 172.18.2.4 metric 103
      route4 172.23.0.0/16 via 172.18.2.4 metric 103
      route4 172.22.0.0/16 via 172.18.2.4 metric 103
```

```
enp8s0: connecting (getting IP configuration) to Wired connection 1
"Red Hat Virtio 1.0"
ethernet (virtio_net), 52:54:00:BD:64:34, hw, mtu 1500

lo: connected (externally) to lo
"lo"
loopback (unknown), 00:00:00:00:00:00, sw, mtu 65536
inet4 127.0.0.1/8
inet6 ::1/128
route6 ::1/128 metric 256
```

```
[mdcadmin@rcpt-nsp-07 ~]$
```

Revision #2

Created 2026-07-22 19:49:25 UTC by poslop

Updated 2026-07-22 20:17:18 UTC by poslop